

## [Windows/macOS] AVer PTZ Link Software Release Notes – September 27, 2021

VERSION	V1.1.1012.0
HARDWARE	The following product models are supported by AVer PTZ Link.
COMPATIBILITY	• TR310/TR311/TR311HN/TR313/TR331/TR333 V0.0.0000.21 and later,
	• TR530/TR320 V0.0.1000.47 and later,
	• PTZ310/PTZ310N/PTZ330/PTZ330N V0.0.0000.56 and later,
	• TR313V2 V0.1.0000.18 and later
OPERATING	Windows <sup>®</sup> 7, 8.1, 10
SYSTEMS	macOS 10.14 and later

V1.1.1012.0	New Features
Release date:	1. Added support for "Sennheiser TeamConnect Ceiling 2" microphone
September 27, 2021	2. Added support for AVer TR313V2 series
	Bug Fixes
	1. Resolved the issue of not supporting macOS 11, this limitation has been fixed.
	2. Resolved the issue of not able to turn on PTZ Link when PC is under 4k resolution,
	this bug has been fixed.
	3. Resolved the issue of unsynchronized indication while microphone is disconnected.
	Known Issues
	1. When more than one channel is detected, camera is not able to support group
	framing.
	• In most meetings and a lot of online classes, conversations go back and forth.
	Sennheiser TeamConnect Ceiling 2 might pick up speakers' voices from all around

the room, causing the camera to go back and forth between different preset
points. If such is the case, you can enable the Priority Zone of Sennheiser
TeamConnect Ceiling 2 so that it only picks up the audio signals of the zone you
chose. For details on the Priority Zone of Sennheiser TeamConnect Ceiling 2, visit:
Setting up Zones for TeamConnect Ceiling 2 (sennheiser-sites.com)
• As for Shure, the second channel will only be "activated/detected" once the
previous speaker stops talking.

V1.1.1009.0	General
Release date:	This release note is only for the announcement of newly supported models that have
May 11, 2021	been fully tested on PTZ Link V1.1.1009.0; Therefore, no exclusive software release is
	needed.
	New Features
	1. The following microphone systems are tested and supported by current release
	version.
	Shure MXA710 microphone
	Shure MXA310 microphone
	*Please note it's a requirement to set up and configure channels for MXA710 on Shure
	Designer software first, so PTZ Link can work properly.
	*Please note using a single channel on the MXA310 is not supported by PTZ Link. To
	operate PTZ Link normally, please add and configure other channels on the MXA310
	webpage.
	Bug Fixes
	The same as previous release note that published on May 11.

Known Issues
The same as previous release note that published on May 11.

V1.1.1009.0	New Features
Release date:	1. The following microphone systems are supported current release version.
May 11, 2021	· Shure IntelliMix <sup>®</sup> P300 processor
	· Shure MXA910 microphone
	2. Able to link AVer cameras to maximum 5 sets of microphone systems.
	3. Able to pair up camera preset points with up to 8 microphone channels.
	4. Able to show camera and microphone status.
	5. Able to configure time to trigger camera to go to preset points that already set up.
	6. Able to configure time to go back to Preset 0 when no microphone channel is
	detected.
	7. Able to support English and Traditional Chinese version of the software.
	Bug Fixes
	None. Initial release.
	Known Issues
	1. When more than one channel is detected, camera is not able to support group
	framing. (*Will support in the next version.)
	2. MacOS lower than ver. 14 currently not supported. MacOS 11 will be added to
	support list in the next version.