

AVer PTZ Link

User Manual



COPYRIGHT

©2021 AVer Information Inc. All rights reserved.

All rights of this object belong to AVer Information Inc. Reproduced or transmitted in any form or by any means without the prior written permission of AVer Information Inc. is prohibited. All information or specifications are subject to change without prior notice.

TRADEMARKS

“AVer” is a trademark owned by AVer Information Inc. Other trademarks used herein for description purpose only belong to each of their companies.

DISCLAIMER

No warranty or representation, either expressed or implied, is made with respect to the contents of this documentation, its quality, performance, merchantability, or fitness for a particular purpose. Information presented in this documentation has been carefully checked for reliability; however, no responsibility is assumed for inaccuracies. The information contained in this documentation is subject to change without notice.

In no event will AVer Information Inc. be liable for direct, indirect, special, incidental, or consequential damages arising out of the use or inability to use this product or documentation, even if advised of the possibility of such damages.

Help

Global

Download Center: <https://www.aver.com/download-center>

Technical Support: <https://www.aver.com/technical-support>

USA

Download Center: <https://www.averusa.com/pro-av/support/>

Technical Support: <https://averusa.force.com/support/s/contactsupport>

Europe

Download Center: <https://www.avereurope.com/download-center>

Technical Support: <https://www.avereurope.com/technical-support>

Contact Information

Global

AVer Information Inc.

<https://www.aver.com>

8F, No.157, Da-An Rd., Tucheng Dist., New Taipei City 23673, Taiwan

Tel: +886 (2) 2269 8535

USA

AVer Information Inc.

<https://www.averusa.com>

668 Mission Ct., Fremont, CA 94539, USA

Tel: +1 (408) 263 3828

Toll-free: +1 (877) 528 7824

Technical support: support.usa@aver.com

European Headquarters

AVer Information Europe B.V.

<https://www.avereurope.com>

Westblaak 134, 3012KM, Rotterdam, The Netherlands

Tel: +31 (0) 10 7600 550

Technical support: eu.rma@aver.com

Contents

PREFACE	1
MINIMUM SYSTEM REQUIREMENT	1
DOWNLOADING THE APPLICATION	2
CONNECTION	2
OPERATION	3
Install AVer PTZ Link.....	3
Link Device	4
Delete Device	9
Edit Device.....	10
Disable Device.....	11
Review Information and Configure Language	12
Minimize and Restore AVer PTZ Link.....	15
Exit AVer PTZ Link.....	16
Troubleshooting	17

PREFACE

AVer PTZ Link is a software to link AVer cameras to microphone system. The supported models are listed below.

AVer tracking cameras (USA region)

- TR310/TR311/TR311HN/TR313
- TR320/TR530/TR320+/TR530+

AVer tracking cameras (non USA region)

- PTC310/PTC310U/PTC310H
- PTC115/PTC500S/PTC115+/PTC500+

AVer PTZ cameras

- PTZ310/PTZ310N/PTZ330/PTZ330N

Microphone system

- Shure IntelliMix® P300 processor
- Shure MXA310 microphone
[Note] Using single channel on MXA310 is not supported by PTZ Link. To operate PTZ Link normally, please add and configure other channels on MXA310 webpage.
- Shure MXA710 microphone
[Note] It is required to set up and configure channels for MXA710 on Shure Designer software first, so PTZ Link can be worked properly.
- Shure MXA910 microphone

MINIMUM SYSTEM REQUIREMENT

PC hardware and software requirement

- CPU: Intel® Core™ 2 Duo 2.00GHz or higher
- RAM: 2GB of RAM or more
- HDD: 100MB (Free Space)
- OS: Windows® 7, 8.1, 10 & macOS v10.14 or later
- Network available

DOWNLOADING THE APPLICATION

Through AVer PTZ Link, user can link AVer cameras to microphone system. Therefore, user needs to install AVer PTZ Link at server (PC/laptop) site and keep AVer PTZ Link running during the meeting.

To get this software, please visit our download center (see below URL) to download.


Global: <https://www.aver.com/download-center>

USA: <https://www.averusa.com/pro-av/support/>

Europe: <https://www.avereurope.com/download-center>

CONNECTION



- Please make sure all devices are well-connected and power on.
- Needs to install “**AVer PTZ Link**” application.
- All devices are suggested on a same LAN, or UDP port – 52381 & TCP port – 2202 must be available between devices.



OPERATION

Install AVer PTZ Link

1. After downloading, double-click  to start installation. Follow the on-screen instructions to complete the installation.




2. After installation, AVer PTZ Link icon  is displayed.
3. Double-click  to launch AVer PTZ Link.

Link Device


1. Enter camera IP (in IPv4 format), camera account, camera password, microphone IP (in IPv4 format), and create a device name (length has to be less than 20 characters) for this paired camera and microphone. Then, click “Link.”

[Notes]



- AVer PTZ Link will memorize the last setting, including device name and preset setup.
- When AVer PTZ Link launches, the paired devices will automatically run.
- Links can be created even for the offline cameras.



When the camera and the microphone have been successfully paired, a message dialog will appear. Click  or  button to close the dialog.




2. Click **Set Preset** button and enter the camera's account and password to sign in the camera's web setting page.




3. In the Live View of web setting page, click **Preset** tab. Enter the preset number in the Save Preset field and use directional and zoom in/out buttons to adjust camera to desired position. Click **Save** button to save the preset position.

[Notes]


- Each camera's web setting page may vary. Please refer to camera's user manual for more details.
- Up to 256 (0~255) preset points can be set up.





4. After setting preset, pair your preset with microphone. Use the drop-down list to select camera preset for each channel (up to 8 channels for each device).




5. Click  button to open a dialog to set up time to trigger preset and time to go back to Preset 0.




Time to trigger Preset (default 1 second) is the detected voice time threshold before camera moving to the preset of that voice. For example, if Time to trigger Preset is set at 3 sec and a speaker has talked longer than 3 seconds, the camera will move to the preset of that speaker. However, if a speaker has talked less than 3 seconds, the camera will not move.


Time to go back to Preset 0 (default 15 minutes) is the time interval between no voice detecting and camera moving to the Preset 0. Click  or  button to confirm. Click  button to close the dialog.




If the voice is detected by any channel, the voice tracking  icon will appear. The Channel in blue indicates that the camera is staying at its preset point.



6. To link more devices, click **Link more devices +** button and repeat above steps.






Up to 5 pairs can be created. If user wants to create more than 5, a warning dialog will appear. Click **OK** or **X** button to close the dialog.




Delete Device

To delete the device, click the drop-down list of device and click  icon.






A warning dialog will appear. Click  or  button to confirm. Click  button to close the dialog.




Edit Device

To edit the device, click the drop-down list of device and click  button.




A set up dialog will appear. Edit the information and click  button. Click  or  button to close the dialog.




Disable Device

To disable the device, click the drop-down list of device and toggle the switch.



The status of device/camera/microphone will become offline and Set Preset button will be disabled.

Status of Device
Green: Online
Gray: Offline




Status of Microphone
Green: Online
Gray: Offline


Status of Camera
Green + Camera Model: Online supported camera with correct camera account and password
Gray + Camera IP: Offline supported/unsupported camera that has never linked before
Gray + Camera Model: Offline supported camera that has linked before
Red + ACC/PW Error: Online camera with incorrect account or password



Review Information and Configure Language


To review version/Privacy Policy/About information or configure the Language, click  button.



The Information dialog will appear. Click the tabs to review or configure. Click  button to close the dialog.









Minimize and Restore AVer PTZ Link

To make voice tracking work during the meeting, AVer PTZ Link must be kept running. User can minimize AVer PTZ Link to system tray to run in background. Click  button to minimize AVer PTZ Link.







To restore, right-click AVer PTZ Link icon on the system tray and select **Open AVer PTZ Link**.




Exit AVer PTZ Link

Click  button or right-click AVer PTZ Link icon on the system tray and select **Exit** to exit AVer PTZ Link.




The warning dialog will appear. Your device will be disconnected if you close the software. Click  or  button to confirm. Click the  button to close the dialog.



Troubleshooting

1. How to set up multiple cameras or microphones with PTZ Link?
 - You can set up a maximum of 5 groups of devices in PTZ Link. For example, when there are two microphones and one camera in the room, you can set two microphones into two groups accordingly. Each microphone has 8 channels that can be matched to 8 different preset points of the camera. One AVer camera has up to 256 preset points available. To make sure the audio tracking functions well, each group has to be enabled and the software is kept running.
2. What microphone brands are supported by PTZ Link?
 - Currently, PTZ Link supports Shure MXA310, MXA710, MXA910 and P300 and we are actively developing partnerships with other brands that bring the audio solution. If other microphone integration with AVer Pro AV cameras in your region is needed, please feel free to let us know. You may contact the [technical support](#) listed on the previous page.
3. How do the Mute functions of Shure microphones work with PTZ Link?
 - If the Mute function of a single channel of the microphone is enabled, the corresponding channel of PTZ Link will not detect the voice.



- If the Mute function is enabled on the webpage of the microphone, it is also required to disable the corresponding device on PTZ Link. Thus, the microphone will not respond in PTZ Link.

